

## ESXI 虚拟机安装 Realtek 瑞昱 RTL8111G/8168 网卡驱动

Realtek 瑞昱的显卡不能识别，

### 1、登录 ESXI6.7 web 管理界面


找到：主机>操作>服务>启用安全 Shell (SSH) 和启动控制台 Shell

下载一个 xshell 调试工具

### 2、下载网卡驱动

<https://vibsdepot.v-front.de/wiki/index.php/Net55-r8168>

找到网页左下角的下载区域，点击下载，如下图



### 3.上传到 esxi 存储

点击 web 管理界面左侧存储选项，主区域找到“数据存储浏览器”，进入图形浏览界面，新建一个文件夹，我建了一个 qudong 的文件夹，然后上传刚刚下载的驱动

这里很关键，查看硬盘路径，如下图



VMFS 详细信息	
版本	6.82
本地	是
块大小	1 MB
UUID	5d00d8cd-63a0054c-95f6-00e06f68011f
数据区 0	t10.ATA_____WDC_WDS120G1G0A2D00SS50_____171409A0091D_____, 分区 3

我们刚刚新建的 qudong 文件夹的路径就是上面红色框+qudong，

即是/vmfs/volumes/5d00d8cd-63a0054c-95f6-00e06f68011f/qudong

驱动程序的路径 /vmfs/volumes/5d00d8cd-63a0054c-95f6-00e06f68011f/qudong/net55-r8168-8.045a-napi.x86\_64.vib

输入命令，查看驱动，红色字体部分就是我们刚上传的驱动程序

```
[root@localhost:~] cd /vmfs/volumes/5d00d8cd-63a0054c-95f6-00e06f68011f/qudong
```

```
[root@localhost:/vmfs/volumes/5d00d8cd-63a0054c-95f6-00e06f68011f/qudong] ls
```

```
net55-r8168-8.045a-napi.x86_64.vib
```

```
[root@localhost:/vmfs/volumes/5d00d8cd-63a0054c-95f6-00e06f68011f/qudong]
```

这个路径很关键，安装指令需要用到

### 4、需要先设置 Level

输入：

```
1 esxcli software acceptance set --level=CommunitySupported
```

## 5、安装驱动

入：

```
1 esxcli software vib install -v /vmfs/volumes/5d00d8cd-63a0054c-95f6-00e06f68011f/qudong/net55-r8168-8.045a-napi.x86_64.vib
```

注意这个命令有点长，只需要替换你自己的路径就可以安装成功了。

下图是整个指令运行情况

```
[root@localhost:/vmfs/volumes] cd /vmfs/volumes/5d00d8cd-63a0054c-95f6-00e06f68011f
[root@localhost:/vmfs/volumes/5d00d8cd-63a0054c-95f6-00e06f68011f] ls
LEDE                               net55-r8168-8.045a-napi.x86_64.vib
ROS                                qudong
[root@localhost:/vmfs/volumes/5d00d8cd-63a0054c-95f6-00e06f68011f] cd qudong
[root@localhost:/vmfs/volumes/5d00d8cd-63a0054c-95f6-00e06f68011f/qudong] ls
net55-r8168-8.045a-napi.x86_64.vib
[root@localhost:/vmfs/volumes/5d00d8cd-63a0054c-95f6-00e06f68011f/qudong] esxcli software acceptance set --level=CommunitySupported
Host acceptance level changed to 'CommunitySupported'.
[root@localhost:/vmfs/volumes/5d00d8cd-63a0054c-95f6-00e06f68011f/qudong] esxcli software vib install -v net55-r8168-8.045a-napi.x86_64.vib
[VibDownloadError]
('net55-r8168-8.045a-napi.x86_64.vib', '/tmp/vib_lpts89kf', "unknown url type: 'net55-r8168-8.045a-napi.x86_64.vib'")
url = net55-r8168-8.045a-napi.x86_64.vib
Please refer to the log file for more details.
[root@localhost:/vmfs/volumes/5d00d8cd-63a0054c-95f6-00e06f68011f/qudong]
[root@localhost:/vmfs/volumes/5d00d8cd-63a0054c-95f6-00e06f68011f/qudong] esxcli software vib install -v /vmfs/volumes/5d00d8cd-63a0054c-95f6-00e06f68011f/qudong/net55-r8168-8.045a-napi.x86_64.vib
Installation Result
Message: The update completed successfully, but the system needs to be rebooted for the changes to be effective.
Reboot Required: true
VIBs Installed: Realtek_bootbank_net55-r8168_8.045a-napi
VIBs Removed:
VIBs Skipped:
[root@localhost:/vmfs/volumes/5d00d8cd-63a0054c-95f6-00e06f68011f/qudong] █
```